

# voice<sup>ely</sup> reader<sup>®</sup>

SERVER 22

## Manual



*Linguatec*  
Language Technologies

## Table of Contents

1	Introduction .....	3
1.1	Technical Support.....	3
1.1.1	Support on the Internet .....	3
1.1.2	Personal Support.....	3
1.1.3	General Questions and Suggestions.....	3
2	System Requirements .....	4
3	Installation .....	4
3.1	Installation from DVD.....	5
3.2	Installation by Download .....	5
3.3	Installing Additional Languages.....	5
4	Product Activation .....	5
4.1	Instant Activation .....	6
4.2	Manual Activation .....	6
5	Uninstalling .....	8
6	Using Voice Reader Server 22.....	8
6.1	Graphical User Interface .....	8
6.2	Interfaces.....	9
6.2.1	HTTP request methods: POST, GET and Web Services .....	9
6.2.2	Windows Communication Foundation (WCF).....	11
7	Appendix.....	12
7.1	Language and Voice Identifier.....	12
7.2	Coding for Audio File Formats.....	16
7.2.1	Coding for WAV Files (format="wav") .....	16
7.2.2	Coding for MP3 Files (format="mp3") .....	17
7.3	Subtitle Formats .....	18
7.4	Voice Markups.....	19

# 1 Introduction

Voice Reader Server 22 is a precise and reliable speech output program that uses remarkably natural sounding voices and is available in many languages. Voice Reader Server 22 converts any of your texts to voice. Audio output can be professionally customized using commands that are inserted directly into the text (Voice Markups). If certain terms are to be assigned a specific pronunciation, or others are to be ignored, the vocabulary can be expanded as needed. This manual will explain how to set up and use Voice Reader Server 22 on a Windows Server.

Thank you for choosing Voice Reader Server 22. We hope you enjoy using it!

For more information on Linguatec and other speech technology products, please visit our homepage at <https://www.linguatec.de/>.

## 1.1 Technical Support

### 1.1.1 Support on the Internet

If you experience any problems that cannot be solved using the manual or the online help, please visit our comprehensive support area on the Internet:

<https://www.linguatec.de/en/services/support-faqs/>

You will find a compilation of the most frequently asked questions (FAQs) there. Experience has shown that it already contains detailed instructions for quickly resolving almost all user questions.

### 1.1.2 Personal Support

If you have a specific problem that cannot be resolved using the FAQs, we will gladly provide you with personal support. Support will be provided via email and is free for registered users, for up to 90 days following the purchase of Voice Reader Server 22. Therefore, please take care to enter your personal information correctly when activating the program.

All questions directed to support must include the following information:

- Program version
- Operating system
- Description of the error, including any error messages received

Please use the support form for your questions:

<https://www.linguatec.de/en/services/supportform/>

### 1.1.3 General Questions and Suggestions

Please contact us if you have any questions regarding additional languages or other language technology products. Use the contact form provided at:

<https://www.linguatec.de/en/contact/>

Your suggestions for Voice Reader Server 22 and this manual are always welcome, and we will make every effort to consider them in the continuing development of our products.

## 2 System Requirements

Before installing Voice Reader Server 22, please make sure that the system requirements are fulfilled:

- Operating System: Windows Server x64, Windows Desktop x64
- Available hard disk space: From 2 Gb depending on the number of installed languages
- Memory: at least 4 GB RAM
- Internet connection for product activation

## 3 Installation

The installation of Voice Reader Server 22 consists of at least two installations:

- Voice Reader Server 22 server software solution
- Voice Reader Server 22 language data (one installation per language)

The first step is the installation of the server software solution. Then the voice data of each acquired Voice Reader Server 22 language must be installed. For each language a separate installation is required.

Please note that you must be logged in as an administrator to install Voice Reader Server 22. Make sure that installed antivirus programs or the firewall are not blocking any processes required for installation. Before starting the installation, save any open documents and close all applications.

During the installation, either the IP address of the server or its DNS name has to be specified, through which the server is addressed from the web browser or through another application via the network. This input will be named as **[HOSTNAME]** in the further description.

The installation detects and installs automatically the following Microsoft Redistributables:

- Microsoft .NET Framework 4.5
- Microsoft Visual C++ 2012
- Microsoft Visual C++ 2017-2019

The installation installs and configures, inter alia, the following features and roles:

### Web Server IIS

- Application Development
  - ASP.NET
  - .NET Extensibility
  - ASP
  - ISAPI Extension
  - ISAPI Filters
- Application Pool „VoiceReaderServer22“, .NET CLR-Version v4.0.30319
- Windows User „VoiceReaderServer22“ in the administrator group.

## 3.1 Installation from DVD

Insert the Voice Reader Server 22 server software solution DVD into your Server's DVD drive to start the installation. In the event that the installation does not start automatically, execute the **setup.exe** file manually. For example: Locate and open the DVD drive in Windows Explorer, then right-click the file **setup.exe** in the DVD folder. From the context menu, choose the option **Run as administrator**. Follow the instructions on your screen.

Then, insert the Voice Reader Server 22 DVD for the installation of the language data into your DVD drive and proceed analogously as for the server software solution installation.

## 3.2 Installation by Download

If you obtained Voice Reader Server 22 as a download, please download the links which have been sent to you by your online vendor and save the Voice Reader Server 22 installation files on your server. Please run the installations not until the download is complete. The size of the server installation is about 170 MB. The size of the language data installation depends on the language and can be up to 1.5 GB. Please start with the server installation.

## 3.3 Installing Additional Languages

If you have already installed Voice Reader Server 22 and now wish to add an additional language, simply run the **VRServer22\_[language].msi** installation wizard with the new language from the DVD or the downloaded folder. The existing installation will be recognized, and the additional language will be installed.

# 4 Product Activation

The unlimited use of Voice Reader Server 22 requires the activation of the product using the license keys provided. You obtain one license key for the server installation and one for the language installation. You will find the 25-character license keys on the DVD or the DVD cover. If you purchased a download version, the online vendor will send the license keys to you following completion of the purchase.

Voice Reader Server 22 and the language installation have to be activated with an activation code within 30 days following installation. The activation code is generated during activation using the license key entered and your computer's hardware code.

As long as Voice Reader Server 22 has not been activated, the Activation Wizard will be displayed each time the program is started. Product activation requires an internet connection.

There is a choice of two activation methods.

- **Instant activation:** If the server on which Voice Reader Server 22 has been installed is connected to the Internet, product activation can be performed online within moments.
- **Manual activation:** In the event that instant activation is not possible (e.g. when the server with Voice Reader Server 22 is not connected to the Internet), you can go online from any other PC to retrieve your activation code on the Linguattec activation website, and then manually transfer it to your server.

## Important notes on product activation

Since it uses a hardware code, the product activation is connected to the server on which Voice Reader Server 22 is installed. The codes that you receive for activation can therefore be used only on the server from which you have initiated product activation and generated the hardware code.

The product must be reactivated after each reinstallation or reconfiguration of Windows Server.


Reactivation will also be required if you install an additional language for Voice Reader Server 22.

## 4.1 Instant Activation

Instant activation requires that the server on which Voice Reader Server 22 has been installed is connected to the internet. If this is the case, this is the preferred method of activation, because - apart from the license key - no further codes need to be entered manually, and product activation is completed within moments.

For up to 30 days following installation, you can use Voice Reader Server 22 without activating the product.

Do the following to perform the activation:

1. Start on a PC which has a network connection to the server a web browser and open this URL:  
[http://\[HOSTNAME\]/VoiceReaderServer22UI/Admin.aspx](http://[HOSTNAME]/VoiceReaderServer22UI/Admin.aspx)
2. In the user interface of Voice Reader Server 22 please click the button „Product Activation“  and then „**Activate now**“.
3. Please enter your license keys for the server installation and the purchased languages in the corresponding lines in the dialog box „Voice Reader Server 22 – Product Activation“.
4. You will find the license keys on the DVDs. If you purchased Voice Reader Server 22 via download, the online vendor will send the license key to you following completion of the purchase. (If you have not yet received the license key, please contact directly your vendor.)
5. Enter your name and your email address. Make sure that they are entered correctly. This is required to receive support and to take advantage of our update offers.
6. Click on the **Continue** button to move on to the next dialogue box. Under **Activation method**, make sure that the option **Instant activation** is selected. Under **Proxy settings**, leave the default option checked (»Do not use a proxy server«), and click on **Continue** to complete activation.
7. You will receive a message confirming successful activation. You now have unlimited access to Voice Reader Server 22 and its activated language on this server.

In case that the connection to the activation server fails, please perform the **manual activation**.


## 4.2 Manual Activation



Perform the manual activation if the server on which Voice Reader Server 22 is installed is not connected to the internet, or if the instant activation has failed. Otherwise, instant activation is simpler and faster.

In the case of manual activation, a hardware code must first be generated on the installation server (s. item 5 below). With this hardware code and your license key, you can use any other PC to access the Linguattec activation website (<https://www.linguattec.de/en/activation/>) to generate an activation code which must then be entered on the installation server to activate the product.

Do the following to perform the activation:

1. Start on a PC which has a network connection to the server a web browser and open this URL:  
[http://\[HOSTNAME\]/VoiceReaderServer22UI/Admin.aspx](http://[HOSTNAME]/VoiceReaderServer22UI/Admin.aspx)
2. In the user interface of Voice Reader Server 22 please click the button „Product Activation“  and then „**Activate now**“.
3. Please enter your license keys for the server installation and the purchased languages in the corresponding lines in the dialog box „Voice Reader Server 22 – Product Activation“.
4. You will find the license keys on the DVDs. If you purchased Voice Reader Server 22 via download, the online vendor will send the license key to you following completion of the purchase. (If you have not yet received the license key, please contact directly your vendor.)
5. Enter your name and your email address. Make sure that they are entered correctly. This is required to receive support and to take advantage of our update offers.
6. Click on the **Continue** button to move on to the next dialogue box. Under **Activation method**, make sure that the option **manual activation** is selected and click on **Continue** to complete activation. (Proxy settings are irrelevant for manual activation.)
7. In the following dialogue, the hardware code required for the generation of the activation codes will be displayed next to the program version. Click on the link **Activation form** to open a HTML document containing the license keys you have entered and the hardware code. Either print this form or save it on a mobile data medium (e.g. USB stick). Should neither be possible, please make a note of the hardware code and your license keys.
8. Connect to the Linguattec activation website (<https://www.linguattec.de/en/activation/>) from any PC and enter your license keys and the hardware code to generate the activation codes.
9. Either print the form containing the activation codes or make a note of the codes on the print out of the activation form. Please make sure to use exactly the same writing, especially the correct upper and lower case.
10. Return to the **Product activation: Manual activation**. If the dialogue has already been closed, please restart the Voice Reader Server 22 URL to bring up the product activation again. Then repeat the steps as described above.
11. Enter the activation codes received on the activation website into the corresponding fields.
12. Click on the **Continue** button to complete the activation.
13. You will receive a message confirming successful activation. You now have unlimited use of Voice Reader Server 22 on that server.

## 5 Uninstalling

To uninstall Voice Reader Server 22, use the standard Windows function.

Depending on the Windows server or PC configuration you may need the original installation files on the installation DVD or in your download file.

## 6 Using Voice Reader Server 22


Voice Reader Server 22 offers several web-based interfaces which can be accessed through a web browser or through own programs via web services interface. Examples of programs in Perl, Python and Java can be found in the installation directory on the server after the installation of Voice Reader Server 22.

During installation either the IP address from the server or its DNS name was entered, via which the server can be accessed over the network from a web browser or from own applications. This entry is named in the manual as **[HOSTNAME]**.

### 6.1 Graphical User Interface

The graphical user interface of Voice Reader Server 22 provides access to administrative tools such as the activation ("Activate"), the dictionary management ("Manage Dictionaries") and the simple reading functionality ("Read text"). It can be achieved in any web browser using the following URL:

[http://\[HOSTNAME\]/VoiceReaderServer22UI/Admin.aspx](http://[HOSTNAME]/VoiceReaderServer22UI/Admin.aspx)



You can enter the desired text into the text box. The "Read text" button will start the text-to-speech process for simple reading. In the boxes for language and voice you can choose between the installed components. Use the slider bar to change the settings for speed, pitch or volume. The reset buttons will change the values to default.

A dictionary can be created and maintained via the Windows desktop version of Voice Reader Studio 15. Via the graphical user interface of Voice Reader Server 22 the dictionary may be imported (button "Manage Dictionaries" - "Upload to server"), exported (button "Manage



Dictionaries " - "Download from server"), enabled (button "Manage Dictionaries " - "Activate") or be deactivated (button "Manage Dictionaries" - "Deactivate").

## 6.2 Interfaces

Voice Reader Server 22 provides the following programming interfaces for direct machine-to-machine interaction:

- HTTP request methods POST and GET
- Web Services: SOAP 1.1 and 1.2
- WCF

### 6.2.1 HTTP request methods: POST, GET and Web Services

A description and a test option for all methods to the HTTP POST and GET interfaces as well as to the Web Services SOAP 1.1 and 1.2 can be reached from any web browser using the following URL:

**[http://\[HOSTNAME\]/VoiceReaderServer22WebService/VRServer22WebService.asmx](http://[HOSTNAME]/VoiceReaderServer22WebService/VRServer22WebService.asmx)**

Method	Beschreibung
GetInstalledLanguages	Returns a list of all languages which are installed on the server.
GetInstalledVoicesForLanguage	Returns a list of all installed voices for a particular language.
GetSupportedLanguages	Provides a list of supported languages for a multilingual voice.
GetSupportedVoices	Provides a list of all installed voices.
ReadPlainText	Converts a certain plain text into a MP3 audio file.
ReadPlainTextEx	Converts a certain plain text with advanced parameters into a particular audio file. The available parameters and audio file formats are listed in the Appendix under: "Codings for Audio File Formats"
ReadPlainTextWithSubtitles	The same as for ReadPlainText: Converts a certain plain text into a MP3 audio file. In addition to the audio file an eponymous subtitle file is generated. The parameters for the generation of specific subtitle files are listed in the Appendix (chapter 7.3)

	under "Subtitle Formats".
ReadPlainTextWithSubtitlesEx	<p>The same as for ReadPlainTextEx: Converts a certain plain text with advanced parameters into a MP3 audio file. In addition to the audio file an eponymous subtitle file is generated.</p> <p>The parameters and the audio file formats are listed in the Appendix (chapter 7.2.) under "Coding for Audio File Formats".</p> <p>The parameters for the generation of specific subtitle files are listed in the Appendix (chapter 7.3) under "Subtitle Formats".</p>
ReadText	<p>Converts a specific text with Voice Markups into a MP3 audio file.</p> <p>The available Voice Markups are listed in the Appendix (chapter 7.4) under „Voice Markups“.</p>
ReadTextEx	<p>Converts a specific text with Voice Markups and advanced parameters into a MP3 audio file.</p> <p>The parameters and the audio file formats are listed in the Appendix (chapter 7.2.) under "Coding for Audio File Formats".</p> <p>The available Voice Markups are listed in the Appendix (chapter 7.4) under „Voice Markups“.</p>
ReadTextWithSubtitles	<p>The same as ReadText.</p> <p>Generates in addition to the audio file an eponymous subtitle file.</p> <p>The parameters for the generation of specific subtitle files are listed in the Appendix (chapter 7.3) under "Subtitle Formats".</p>
ReadTextWithSubtitlesEx	<p>The same as ReadTextEx.</p> <p>Generates in addition to the audio file an eponymous subtitle file.</p> <p>The parameters and the audio file formats are listed in the Appendix (chapter 7.2.) under "Coding for</p>

	<p>Audio File Formats”.</p> <p>The available Voice Markups are listed in the Appendix (chapter 7.4) under „Voice Markups“.</p>
RemoveFile	Deletes a specific audio file and the associated subtitle file.

Examples of programs in Perl, Python and Java can be found in the installation directory on the server after the installation of Voice Reader Server 22. For the application the variable „urlService“ or „URL\_SERVICE“ must be adapted to the corresponding [HOSTNAME].

## 6.2.2 Windows Communication Foundation (WCF)

The **WCF**-Interface is accessible via the following URL:

**[http://\[HOSTNAME\]/VoiceReaderServer22WcfService/TtsWcfService.svc](http://[HOSTNAME]/VoiceReaderServer22WcfService/TtsWcfService.svc)**

The **WSDL** document can be opened with this HTTP call in a browser:

**[http://\[HOSTNAME\]/VoiceReaderServer22WcfService/TtsWcfService.svc?wsdl](http://[HOSTNAME]/VoiceReaderServer22WcfService/TtsWcfService.svc?wsdl)**

With the help of the Service Model Metadata Utility Tool (svcutil.exe) configurations and code files to a particular server can be generated. For further information, look up the following terms on the MSDN page:

- Windows Communication Foundation Tools
- ServiceModel Metadata Utility Tool (Svcutil.exe)
- Generating a WCF Client from Service Metadata

## 7 Appendix

### 7.1 Language and Voice Identifier

Any available language of Voice Reader Server 22 has its own coding (**lang**), which can be used as a parameter e.g. in a **Voice Markup** to define the reading language. And also each voice of Voice Reader Server 22 has its own coding (**voice**).

Language	Coding (lang)	Voice	Gender
Arabic	arw	Tarik	M
Arabic	arw	Maged-ML	M
Arabic	arw	Laila	F
Arabic (Gulf Region)	arg	Mariam	F
Bengali (India)	bei	Paya	F
Bulgarian	bgb	Daria	F
Croatian	hrh	Lana	F
Basque	bae	Miren	F
Danish	dad	Sara	F
Danish	dad	Magnus	M
German	ged	Anna-ML	F
German	ged	Petra-ML	F
German	ged	Yannick	M
German	ged	Markus	M
German	ged	Viktor	M
English (American)	enu	Ava-ML	F
English (American)	enu	Samantha	F
English (American)	enu	Tom	M
English (American)	enu	Evan	M
English (American)	enu	Nathan	M
English (American)	enu	Zoe-ML	F
English (Australian)	ena	Karen	F
English (Australian)	ena	Lee	M

English (Australian)	ena	Matilda	F
English (British)	eng	Serena	F
English (British)	eng	Daniel	M
English (British)	eng	Kate	F
English (British)	eng	Oliver	M
English (British)	eng	Malcom	M
English (British)	eng	Stephanie	F
English (Indian)	eni	Veena	F
English (Indian)	eni	Rishi-ML	M
English (Indian)	eni	Sangeeta	F
English (Indian)	eni	Isha-ML	F
English (Irish)	ene	Moira	F
English (Scottish)	ens	Fiona	F
English (South African)	enz	Tessa	F
Finnish	fif	Satu	F
Finnish	fif	Onni	M
French	frf	Audrey-ML	F
French	frf	Aurelie	F
French	frf	Thomas	M
French (Canadian)	frc	Amelie-ML	F
French (Canadian)	frc	Nicolas	M
French (Canadian)	frc	Chantal	F
French (Belgium)	frb	Aude	F
Galician	gle	Carmela	F
Greek	grg	Melina	F
Greek	grg	Nikos	M
Hebrew	hei	Carmit	F
Hindi	hii	Lehka	F
Hindi	hii	Neel-ML	M
Hindi	hii	Kiyara-ML	F
Indonesian (Bahasa)	idi	Damayanti	F
Italian	iti	Alice-ML	F

Italian	iti	Federica-ML	F
Italian	iti	Paola	F
Italian	iti	Luca	M
Italian	iti	Emma	F
Japanese	jpj	Ayane	F
Japanese	jpj	Daisuke	M
Japanese	jpj	Ichiro	M
Japanese	jpj	Mizuki	F
Japanese	jpj	Sakura	F
Japanese	jpj	Kogharu	F
Japanese	jpj	Seiji	M
Cantonese (Hongkong)	cah	Sin-Ji-ML	F
Cantonese (Hongkong)	cah	Aasing-ML	M
Kannada (India)	kai	Alpana	F
Catalan	cae	Montserrat	F
Catalan	cae	Jordi	M
Korean	kok	Sora	F
Korean	kok	Yuna-ML	F
Korean	kok	Nuri-ML	F
Korean	kok	Minsu	M
Korean	kok	Jina	F
Malay	msm	Amira	F
Dongbei (China)	doc	Dongmei-ML	F
Mandarin (China)	mnc	Tian-Tian-ML	F
Mandarin (China)	mnc	Li-Li-ML	F
Mandarin (China)	mnc	Bin-Bin-ML	M
Mandarin (China)	mnc	Ban-Ban-ML	M
Mandarin (China)	mnc	Bo-Bo-ML	M
Mandarin (China)	mnc	Han-ML	M
Mandarin (China)	mnc	Lan-Lan-ML	F
Mandarin (China)	mnc	Li-Lian-ML	F
Mandarin (China)	mnc	Li-Sheng-ML	F



Mandarin (China)	mnc	Shan-Shan-ML	F
Mandarin (China)	mnc	Sha-Sha-ML	F
Mandarin (China)	mnc	Tao-Tao-ML	M
Mandarin (China)	mnc	Ting-Ting-ML	F
Mandarin (Taiwan)	mnt	Mei-Jia-ML	F
Marathi	mai	Ananya	F
Dutch (Netherlands)	dun	Claire-ML	F
Dutch (Netherlands)	dun	Xander	M
Dutch (Belgium)	dub	Ellen	F
Norwegian	non	Nora	F
Norwegian	non	Henrik	M
Polish	plp	Ewa	F
Polish	plp	Zosia	F
Polish	plp	Krzysztof	M
Portuguese	ptp	Catarina	F
Portuguese	ptp	Joana	F
Portuguese	ptp	Joaquim	M
Portuguese (Brazilian)	ptb	Luciana	F
Portuguese (Brazilian)	ptb	Felipe	M
Portuguese (Brazilian)	ptb	Fernanda	F
Romanian	ror	Ioana	F
Russian	rur	Milena	F
Russian	rur	Yuri	M
Russian	rur	Katya-ML	F
Swedish	sws	Alva	F
Swedish	sws	Oskar	M
Swedish	sws	Klara	F
Slovak	sks	Laura	F
Spanish	spe	Marisol-ML	F
Spanish	spe	Monica-ML	F
Spanish	spe	Jorge	M
Spanish (Chile)	spl	Francisca	F

Spanish (Colombian)	spc	Soledad	F
Spanish (Colombian)	spc	Carlos	M
Spanish (Mexican)	spm	Paulina-ML	F
Spanish (Mexican)	spm	Angelica	F
Spanish (Mexican)	spm	Juan	M
Spanish (Argentine)	spa	Diego	M
Spanish (Argentine)	spa	Isabela	F
Tamil	tai	Vani	F
Telugu	tei	Geeta	F
Thai	tht	Kanya	F
Thai	tht	Narisa	F
Czech	czc	Iveta	F
Czech	czc	Zuzana-ML	F
Turkish	trt	Yelda	F
Turkish	trt	Cem-ML	M
Hungarian	huh	Mariska	F
Valencian	vae	Empar	F
Persian (Farsi)	fai	Dariush	M
Vietnamese	viv	Linh	F
Ukrainian	uku	Lesya	F
Slovenian	sls	Tina	F
Sichuanese	sic	Fangfang-ML	F
Sichuanese	sic	Feifei	F
Shanghainese (China)	Shc	Lulu-ML	F
Shaanxi (China)	sxc	Hao-Hao	M

## 7.2 Coding for Audio File Formats

### 7.2.1 Coding for WAV Files (format="wav")

Value (coding)	Description
0	8 KHz, 8 Bit

1	8 KHz, 16 Bit
2	11 KHz, 8 Bit
3	11 KHz, 16 Bit
4	22 KHz, 8 Bit
5	22 KHz, 16 Bit, <b>(Standard)</b>
6	44 KHz, 8 Bit
7	44 KHz, 16 Bit
8	48 KHz, 8 Bit
9	48 KHz, 16 Bit

### 7.2.2 Coding for MP3 Files (format="mp3")

Value (coding)	Bit Rate
0	16 kB/s
1	24 kB/s
2	32 kB/s
3	40 kB/s
4	48 kB/s
5	56 kB/s
6	64 kB/s <b>(Standard)</b>
7	80 kB/s
8	96 kB/s
9	112 kB/s
10	128 kB/s
11	160 kB/s

## 7.3 Subtitle Formats

<b>Value (typeSubtitles)</b>	<b>Subtitle Format</b>
0	No file
1	VVT file with sentence segmentation
2	VVT file with word segmentation
3	SRT file with sentence segmentation
4	SRT file with word segmentation

## 7.4 Voice Markups

Markup	Description and examples
lang	<p>Changes the reading language within a multilingual voice.</p> <p><i>&lt;Lang=eng/&gt;Maidstone&lt;Lang=END_eng/&gt;</i></p> <p>Coding for the languages: Please see „Language and Voice Identifier“ in the Appendix (chapter 7.1)</p>
voice	<p>Switches the voice. If the voice belongs to a different language, also the language will be changed.</p> <p><i>&lt;Voice=Susan/&gt;Please dial “one” for further information.&lt;Voice=END_Susan/&gt;&lt;Voice=Petra/&gt;Wenn Sie weitere Informationen wünschen, drücken Sie bitte die „Eins“. &lt;Voice=END_Petra/&gt;</i></p> <p>Coding for the voices: Please see „Language and Voice Identifier“ in the Appendix (chapter 7.1)</p>
speed	<p>Changes the speed of the voice output. The default value is 100.</p> <p><i>This is spoken normally, &lt;Speed=90/&gt;and now I’m talking slower,&lt;Speed=END_90/&gt; &lt;Speed=120/&gt;or faster.&lt;Speed=END_120/&gt;</i></p>
pitch	<p>Changes the pitch of the voice output. The default value is 100.</p> <p><i>&lt;Pitch=80/&gt;lowers the pitch to 80% of the standard pitch &lt;Pitch=END_80/&gt;</i></p>
volume	<p>Changes the volume of the voice output. The default value is 100.</p> <p><i>&lt;Volume=70/&gt;will read more quietly. &lt;Volume=END_70/&gt;</i></p>
pause	<p>Creates a reading pause. The duration of the pause is specified in milliseconds.</p> <p><i>When I am reflecting, &lt;Pause=520/&gt;I make a longer pause.</i></p>